



SKIPINNISH

TECH RIDER
2023



WH 1 / PIPES 1



WH 2 / PIPES 2



C VOX / Ac
GTR



FIDDLE 1 / 2



ACCORDION / SL
VOX



STAGE REQUIREMENTS:

- Please supply 3 band risers - 8ft x 8ft at 1 ft height (on locking rollers where necessary).
- Please supply clean, 13 amp, 230v backline power at ALL stage positions.

AUDIO REQUIREMENTS:

A professional level FOH system of reputable brand (L'Acoustics; D&B etc) is required, in full working order, flown where possible and arrayed to provide complete coverage for ALL audience members (including delays and in/out-fills where appropriate). System must be supplied with 2 competent, sober, English speaking system technicians (1 x FOH, 1x Mons).

2 x audio consoles from the following list: 1 x FOH, 1 x Monitors.

A&H DLive
Midas Pro Series
Yamaha CL Series
Digco SD Series

Please advise any venue/regional/national SPL limits for our show with you within two weeks of show day. Please include details of weighting; timing and position of measurement in the venue. Please also provide a working, recently calibrated class 1 measurement device with a suitable indication of db limit/weighting/time period at the FOH mix position from load-in and for the duration of the entire show.

SKIPINNISH require 8 x wireless IEM mixes, 1 x stereo hardwire IEM and 1 x thumper. Transmitters and packs are supplied unless otherwise stated in the show advance. No less than 11 mixes onstage please. Additional sidefill mixes will be required for larger/outdoor stages. Please see attached for mix/output information. Please advise of local RF licensing requirements in your area during show advance.

See microphone/D.I requirements on the channel list. If any of this is not possible, please contact us at your earliest convenience with alternatives. Thanks for your help and we look forward to working with you. Cheers!

SKIPINNISH

INPUT LIST

Input	Instrument	Mic/DI	+48v	Stand	Location	Notes
1	Kick In	Senn 901/ Beta 91	+48v		DRUM RISER	
2	Kick Out	D6		Short Boom	DRUM RISER	
3	Snare Top	Beta 57		Short Boom	DRUM RISER	
4	Snare Under	KM184	+48v	LP Claw	DRUM RISER	
5	Hats	KM184	+48v	Short Boom	DRUM RISER	
6	Rack Tom 1	E904			DRUM RISER	
7	Rack Tom 2	E904			DRUM RISER	
8	Floor Tom	E904			DRUM RISER	
9	Ride	KM184	+48v	Short Boom	DRUM RISER	
10	OH SR	KM184	+48v	LP Claw	DRUM RISER	
11	OH SL	KM184	+48v	LP Claw	DRUM RISER	
12	Bass	Active DI	+48v		BASS/GTR RISER USL	
13	Elec. Gtr L	E906		Short Boom	BASS/GTR RISER USL	
14	Elec. Gtr R	E906		Short Boom	BASS/GTR RISER USL	
15	Acoustic Gtr	Active DI	+48v		DSC	
16	Keys L	Active DI	+48v		KEYS RISER USR	
17	Keys R	Active DI	+48v		KEYS RISER USR	
18	Synth L	Active DI	+48v		KEYS RISER USR	
19	Synth R	Active DI	+48v		KEYS RISER USR	
20	Whistle 1	Beta 58	+48v	Tall Boom	DSR	*Additional XLR required for mute pedal*
21	Pipes 1	XLR	+48v		DSR	*Additional XLR required for mute pedal*
22	Whistle 2	Beta 58	+48v	Tall Boom	DSR	*Additional XLR required for mute pedal*
23	Pipes 2	XLR	+48v		DSR	*Additional XLR required for mute pedal*
24	Fiddle 1	Active DI	+48v		DSL	
25	Fiddle 2	Active DI	+48v		DSL	
26	Accordion 1	SM58		Short Boom	DSL	

Input	Instrument	Mic/DI	+48v	Stand	Location	Notes
27	Accordion 2	XLR	+48v		DSL	
28	Centre Vocal	E935		Tall Boom	DSC	
29	SL Vocal	E935		Tall Boom	DSL	
30	Keys Vocal	E935		Tall Boom	KEYS RISER USR	
31	Bass Vocal	E935		Tall Boom	BASS/GTR RISER USL	
32	Gtr Vocal	E935		Tall Boom	BASS/GTR RISER USL	
32	Guest 1					**TBD on show advance**
33	Guest 2					**TBD on show advance**
34	Guest 3					**TBD on show advance**
35	Guest 4					**TBD on show advance**
...						
45	Ambient SR	C414	+48v			
46	Ambient SL	C414	+48v			
47	Monitor TTS	SM58 w/ switch				Required send to FOH shout speaker
48	FOH TTS	SM58 w/ switch				Required send to Mons shout speaker

SKIPINNISH

OUTPUT LIST

Mix No.	INSTRUMENT/STAGE POSITION	CONSOLE OUTPUT	NOTES
1	WHISTLE/PIPES 1 - DSR	1	WIRELESS IEM
2	WHISTLE/PIPES 2 - DSR	2	WIRELESS IEM
3	CENTRE VOCAL/AC GTR - DSC	3	WIRELESS IEM
4	FIDDLE - DSL	4	WIRELESS IEM
5	SL VOCAL/ACCORDION DSL	5	WIRELESS IEM
6	KEYS - KEYS RISER - USR	6	WIRELESS IEM
7	BASS - BASS/GTR RISER - USL	7	WIRELESS IEM
8	E.GTR - BASS/GTR RISER - USL	8	WIRELESS IEM
9	DRUMS LEFT - DRUM RISER	9	HARDWIRE IEM XLR
10	DRUMS RIGHT - DRUM RISER	10	HARDWIRE IEM XLR
11	THUMPER - DRUM RISER	11	HARDWIRE XLR
12	SIDEFILL SR	12	*TBD ON SHOW ADVANCE*
13	SIDEFILL SL	13	*TBD ON SHOW ADVANCE*
14	GUEST IEM 1	14	*TBD ON SHOW ADVANCE*
15	GUEST IEM 2	15	*TBD ON SHOW ADVANCE*

CONTACT INFO:

Worldwide:
info@skipinnish.com

Europe
(except Scotland & Denmark)

Barry Stewart
Midnight Mango
barry@midnightmango.co.uk
Tel +49 30 50340409
Mobile +49 163 9755705
www.midnightmango.co.uk